


Migrating from the Automated Test Suite to the Automation Library

Migrating from the ATS to the Automation Library is a simple 3 step process. The new Automation Library will automatically appear in your update client if you are a current user of the ATS.

1) Run the MyUpdater and Install the Automation library



Name	Published On	Action	Setup
Automation Library	2015/12/09		<u>Install</u>
Automated Testing Suite	2017/01/20	Browse	Remove
GFortran 4.6	2013/05/01		<u>Install</u>
PSCAD 4.6.1 (64-bit)	2015/12/09		<u>Install</u>

2) In each of your Python user scripts, change the **System Path** to use the new Automation Library.

Note: This path is near the top of your script.


Old Path

sys.path.append(r"C:\Program Files (x86)\AutomatedTestSuite")

New Path

sys.path.append(r"C:\Program Files (x86)\PSCAD\Automation\Lib\mhrc")

3) Now your scripts will point to the new Automation Library and you can uninstall the Automated Test Suite.



Copyright © 2018 Manitoba Hydro International. All Rights Reserved.